

SGD#	
LSID#	
Laboratory use only	

Chain of Custody

Private Well Analysis

Client Name & Address:	
Phone Number:	Fax Number:
Sample Information: Locat Date/Time Water Last Us Date/Time Water Collecte	ed:
2)	Bacteria FHA/VA Loan Private Well List
FHA/VA Test: Lead, (first f	lush), Nitrate, Nitrite, Bacteria
•	st flush), Copper (first flush), pH, Bacteria, Nitrate, Nitrite, oride, Total Hardness, Turbidity, Color, Arsenic, Iron,
Odor: Yes:No:	Comment (if yes)
Relinquished by:	Date/Time:
Received by:	Date/Time:
Relinquished by:	Date/Time:
Received by:	Date/Time:
Email Address:	

124 W. McIver Road Florence, SC 29501 phone:843-665-6746 fax: 843-656-2208

Davis & Brown

Information & Instructions for Private Well Analysis

- * No samples are accepted on Fridays or the day before holidays.
- * Follow these instructions for FHA/VA and Private Well list.

 (If sampling for bacteria only, skip steps 3 and 4)
 - 1) Get bottle set from laboratory
 - 2) Flush lines for at least 15 minutes from the kitchen faucet.
 - 3) Leave water undisturbed for at least 6 hours, but no more than 12 hours.
 - 4) Collect a "first flush" grab sample from the kitchen faucet, fill the bottle to the rim.
 - 5) Then sterilize the faucet with alcohol inside and outside.
 - 6) Let water run for at least 2 minutes, then fill remaining 2 containers with water.
 - 7) Put samples in a cooler with ice/pack and return to lab with completed form.
- * There must be no chlorine present at time of sample collection.
- * All lines must be completed on the chain of custody for analysis to begin.

Standard turn around time is 10 days.

2020

Costs:	Bacteria (only)	\$ 75.00
	FHA/VA Bacteria, Lead Nitrate, Nitrite	\$ 135.00
	FHA/VA Rush (3 to 5 days)	\$ 180.00
	FHA/VA Rush (48 hours)	\$ 230.00
	Private Well List(recommended)	\$ 262.00

Mailing address: P.O. Box 15038 Quinby, SC 29506 phone: 843-665-6746

^{*} Payment must be received before results will be released.